




binfmt_misc/qemu-user-static misc

原创

 hushui 于 2020-07-17 09:37:42 发布  894  收藏 1

分类专栏: [Qemu Linux ARM](#)

版权声明: 本文为博主原创文章, 遵循 [CC 4.0 BY-SA](#) 版权协议, 转载请附上原文出处链接和本声明。

本文链接: <https://blog.csdn.net/hushui/article/details/107400619>

版权



[Qemu](#) 同时被 3 个专栏收录

26 篇文章 0 订阅

订阅专栏



[Linux](#)

121 篇文章 0 订阅

订阅专栏



[ARM](#)

36 篇文章 0 订阅

订阅专栏

Install Refer to

Qemu2.x user mode/Ubuntu18 for Chroot/ARM qemu-user-static/CONFIG_BINFMT_MISC/Ubuntu/ARM/Rootfs

<https://blog.csdn.net/hushui/article/details/103791704>

Qemu4 user mode source build/static for Chroot/ARM rootfs on Ubuntu18

<https://blog.csdn.net/hushui/article/details/103806109>

```
### normal build with full Linux system emulation
./configure --target-list=aarch64-softmmu,arm-softmmu,x86_64-softmmu,i386-softmmu,aarch64-linux-user,arm-l

### qemu-user-static build for arm/aarch64 only
./configure --target-list=aarch64-linux-user,arm-linux-user --enable-debug --enable-gtk --enable-vnc --
```

On Centos7/RHEL7 qemu-user-static(v4.2) are built from source. (Refer to <https://blog.csdn.net/hushui/article/details/103806109>)

Note for Centos7/RHEL7 , static lib files are needed!

```
yum install gtk2-devel glib2-static
yum install glibc-static libtool
yum install zlib-static
yum install libstdc++-static
yum install pcre-static
```

--disable-guest-agent if Centos misses some pixman static lib

```
[lake@lake_centos7 qemu-4.2.0]$ ./configure --target-list=aarch64-linux-user,arm-linux-user --enable-deb
```

Qemu/static build/old way

```
./configure --disable-bsd-user --disable-guest-agent --disable-strip --disable-werror --disable-gcrypt --d
```

> **qemu-arm version 4.2.0**

1. Enable/disable by /proc/sys/fs/binfmt_misc/status

```
[root@lake_centos7 nfs]# ls /proc/sys/fs/binfmt_misc/  
register status  
[root@lake_centos7 nfs]# cat /proc/sys/fs/binfmt_misc/status  
enabled  
[root@lake_centos7 nfs]# cat /proc/sys/fs/binfmt_misc/register  
cat: /proc/sys/fs/binfmt_misc/register: Invalid argument
```

Try qemu-aarch64

2.1 qemu-aarch64

```
[root@lake_centos7 nfs]#
```

```
echo ":qemu-aarch64:M::\x7fELF\x02\x01\x01\x00\x00\x00\x00\x00\x00\x00\x02\x00\xb7\x00:\xff\xff\xff
```

```
[root@lake_centos7 nfs]# ls -l /proc/sys/fs/binfmt_misc/
total 0
-rw-r--r-- 1 root root 0 Jul 17 01:33 qemu-aarch64
--w----- 1 root root 0 Jul 17 01:33 register
-rw-r--r-- 1 root root 0 Jul 17 01:32 status
[root@lake_centos7 nfs]# cat /proc/sys/fs/binfmt_misc/qemu-aarch64
enabled
interpreter /usr/bin/qemu-aarch64
flags:
offset 0
magic 7f454c460201010000000000000000000000200b700
mask ffffffff00ffffffffffffffefffff
[root@lake_centos7 nfs]#
```

```
echo 0 > /proc/sys/fs/binfmt_misc/<name> # Disable the match
echo 1 > /proc/sys/fs/binfmt_misc/<name> # Enable the match
echo -1 > /proc/sys/fs/binfmt_misc/<name> # Delete the match
```

```
[root@lake_centos7 nfs]# echo 0 > /proc/sys/fs/binfmt_misc/qemu-aarch64
[root@lake_centos7 nfs]# cat /proc/sys/fs/binfmt_misc/qemu-aarch64
disabled
interpreter /usr/bin/qemu-aarch64
flags:
offset 0
magic 7f454c460201010000000000000000000000200b700
mask ffffffff00ffffffffffffffefffff
[root@lake_centos7 nfs]# echo -1 > /proc/sys/fs/binfmt_misc/qemu-aarch64
[root@lake_centos7 nfs]# cat /proc/sys/fs/binfmt_misc/qemu-aarch64
cat: /proc/sys/fs/binfmt_misc/qemu-aarch64: No such file or directory
[root@lake_centos7 nfs]# ls -l /proc/sys/fs/binfmt_misc
total 0
--w----- 1 root root 0 Jul 17 01:33 register
-rw-r--r-- 1 root root 0 Jul 17 01:32 status
[root@lake_centos7 nfs]#
```

2.2 qemu-arm

```
[root@lake_centos7 nfs]#
```

```
echo ' :arm:M: :\x7fELF\x01\x01\x01\x00\x00\x00\x00\x00\x00\x00\x00\x00\x02\x00\x28\x00: \xff\xff\xff\xff\x
```

```
[root@lake_centos7 nfs]#
##### Name
```

```
echo
':arm:M::\x7fELF\x01\x01\x01\x00\x00\x00\x00\x00\x00\x00\x00\x00\x00\x02\x00\x28\x00:\xff\xff\xff\xff\xff\xff\xff\x00\xff
wrapper:' > /proc/sys/fs/binfmt_misc/register
==> /proc/sys/fs/binfmt_misc/arm
```

```
echo ':qemu-
arm:M::\x7fELF\x01\x01\x01\x00\x00\x00\x00\x00\x00\x00\x00\x00\x00\x02\x00\x28\x00:\xff\xff\xff\xff\xff\xff\xff\x00\xff\
arm:' > /proc/sys/fs/binfmt_misc/register
==> /proc/sys/fs/binfmt_misc/qemu-arm
```

```
#####
```

```
[root@lake_centos7 nfs]#
[root@lake_centos7 nfs]# cat /proc/sys/fs/binfmt_misc/qemu-arm
enabled
interpreter /usr/bin/qemu-arm
flags:
offset 0
magic 7f454c4601010100000000000000000000002002800
mask ffffffff00ffffffffffffffe
[root@lake_centos7 nfs]# sudo echo ":qemu-
aarch64:M::\x7fELF\x02\x01\x01\x00\x00\x00\x00\x00\x00\x00\x00\x00\x00\x02\x00\xb7\x00:\xff\xff\xff\xff\xff\xff\xff\x00
aarch64:" > /proc/sys/fs/binfmt_misc/register
[root@lake_centos7 nfs]# ls -l /proc/sys/fs/binfmt_misc/
total 0
-rw-r--r-- 1 root root 0 Jul 17 01:38 qemu-aarch64
-rw-r--r-- 1 root root 0 Jul 17 01:37 qemu-arm
--w----- 1 root root 0 Jul 17 01:38 register
-rw-r--r-- 1 root root 0 Jul 17 01:32 status
[root@lake_centos7 nfs]#
```

4. Mount Ubuntu ARM ROOTFS on Intel X86_64

Refer to <https://blog.csdn.net/hushui/article/details/103791704>